```
3. Producer/consumer example:

    /*
    "buffer" stores BUFFER_SIZE items
    "count" is number of used slots. a variable that lives in memory
    "out" is next empty buffer slot to fill (if any)
    "in" is oldest filled slot to consume (if any)
    */

     void producer (void *ignored) {
         for (;;) {
             /* next line produces an item and puts it in nextProduced */
             nextProduced = means_of_production();
             while (count == BUFFER_SIZE)
                 ; // do nothing
             buffer [in] = nextProduced;
             in = (in + 1) % BUFFER_SIZE;
             count++;
         }
     }

     void consumer (void *ignored) {
         for (;;) {
             while (count == 0)
                 ; // do nothing
             nextConsumed = buffer[out];
             out = (out + 1) % BUFFER_SIZE;
             count--;
             /* next line abstractly consumes the item */
             consume_item(nextConsumed);
         }
     }

    /*
       what count++ probably compiles to:
        reg1 <-- count      # load
        reg1 <-- reg1 + 1   # increment register
        count <-- reg1      # store

       what count-- could compile to:
        reg2 <-- count      # load
        reg2 <-- reg2 - 1   # decrement register
        count <-- reg2      # store
    */

    What happens if we get the following interleaving?

        reg1 <-- count
        reg1 <-- reg1 + 1
        reg2 <-- count
        reg2 <-- reg2 - 1
        count <-- reg1
        count <-- reg2
```



```
4. Some other examples. What is the point of these?

    [From S.V. Adve and K. Gharachorloo, IEEE Computer, December 1996,
    66-76. http://rsim.cs.uiuc.edu/~sadve/Publications/computer96.pdf]

    a. Can both "critical sections" run?

        int flag1 = 0, flag2 = 0;

        int main () {
            tid id = thread_create (p1, NULL);
            p2 (); thread_join (id);
        }

        void p1 (void *ignored) {
            flag1 = 1;
            if (!flag2) {
                critical_section_1 ();
            }
        }

        void p2 (void *ignored) {
            flag2 = 1;
            if (!flag1) {
                critical_section_2 ();
            }
        }

    b. Can use() be called with value 0, if p2 and p1 run concurrently?

        int data = 0, ready = 0;

        void p1 () {
            data = 2000;
            ready = 1;
        }
        int p2 () {
            while (!ready) {}
            use(data);
        }

    c. Can use() be called with value 0?

        int a = 0, b = 0;

        void p1 (void *ignored) { a = 1; }

        void p2 (void *ignored) {
          if (a == 1)
            b = 1;
        }

        void p3 (void *ignored) {
          if (b == 1)
            use (a);
        }
```