


# Machine



Mar 29, 21 5:43

**handout10-1.txt**

Page 1/5

```

1 CS 202, Spring 2021
2 Handout 10 (Class 16)
3
4 1. Example use of I/O instructions: boot loader
5
6 Below is the WeensyOS boot loader
7
8 It may be helpful to understand the overall picture
9
10 This code demonstrates I/O, specifically with the disk: the
11 bootloader reads in the kernel from the disk.
12
13 See the functions boot_waitdisk() and boot_readsect(). Compare to
14 Figures 36.5 and 36.6 in OSTEP.
15
16 /* boot.c */
17 #include "x86-64.h"
18 #include "elf.h"
19
20 // boot.c
21 //
22 // WeensyOS boot loader. Loads the kernel at address 0x40000 from
23 // the first IDE hard disk.
24 //
25 // A BOOT LOADER is a tiny program that loads an operating system into
26 // memory. It has to be tiny because it can contain no more than 510 bytes
27 // of instructions: it is stored in the disk's first 512-byte sector.
28 //
29 // When the CPU boots it loads the BIOS into memory and executes it. The
30 // BIOS initializes devices and CPU state, reads the first 512-byte sector of
31 // the boot device (hard drive) into memory at address 0x7C00, and jumps to
32 // that address.
33 //
34 // The boot loader is contained in bootstart.S and boot.c. Control starts
35 // in bootstart.S, which initializes the CPU and sets up a stack, then
36 // transfers here. This code reads in the kernel image and calls the
37 // kernel.
38 //
39 // The main kernel is stored as an ELF executable image starting in the
40 // disk's sector 1.
41
42 #define SECTORSIZE      512
43 #define ELFHDR          ((elf_header*) 0x10000) // scratch space
44
45 void boot(void) __attribute__((noreturn));
46 static void boot_readsect(uintptr_t dst, uint32_t src_sect);
47 static void boot_readseg(uintptr_t dst, uint32_t src_sect,
48                         size_t filesz, size_t memsz);
49
50 // boot
51 // Load the kernel and jump to it.
52 void boot(void) {
53     // read 1st page off disk (should include programs as well as header)
54     // and check validity
55     boot_readseg((uintptr_t) ELFHDR, 1, PAGESIZE, PAGESIZE);
56     while (ELFHDR->e_magic != ELF_MAGIC) {
57         /* do nothing */
58     }
59
60     // load each program segment
61     elf_program* ph = (elf_program*) ((uint8_t*) ELFHDR + ELFHDR->e_phoff);
62     elf_program* eph = ph + ELFHDR->e_phnum;
63     for (; ph < eph; ++ph) {
64         boot_readseg(ph->p_va, ph->p_offset / SECTORSIZE + 1,
65                     ph->p_filesz, ph->p_memsz);
66     }
67
68     // jump to the kernel
69     typedef void (*kernel_entry_t)(void) __attribute__((noreturn));
70     kernel_entry_t kernel_entry = (kernel_entry_t) ELFHDR->e_entry;
71     kernel_entry();
72 }

```

Mar 29, 21 5:43

**handout10-1.txt**

Page 2/5

```

74
75 // boot_readseg(dst, src_sect, filesz, memsz)
76 //   Load an ELF segment at virtual address 'dst' from the IDE disk's sector
77 //   'src_sect'. Copies 'filesz' bytes into memory at 'dst' from sectors
78 //   '[src_sect' and up, then clears memory in the range
79 //   '[dst+filesz, dst+memsz)'.
80 static void boot_readseg(uintptr_t ptr, uint32_t src_sect,
81                         size_t filesz, size_t memsz) {
82     uintptr_t end_ptr = ptr + filesz;
83     memsz += ptr;
84
85     // round down to sector boundary
86     ptr &= ~(SECTORSIZE - 1);
87
88     // read sectors
89     for (; ptr < end_ptr; ptr += SECTORSIZE, ++src_sect) {
90         boot_readsect(ptr, src_sect);
91     }
92
93     // clear bss segment
94     for (; end_ptr < memsz; ++end_ptr) {
95         *(uint8_t*) end_ptr = 0;
96     }
97 }
98
99
100 // boot_waitdisk
101 //   Wait for the disk to be ready.
102 static void boot_waitdisk(void) {
103     // Wait until the ATA status register says ready (0x40 is on)
104     // & not busy (0x80 is off)
105     while ((inb(0x1F7) & 0xC0) != 0x40) {
106         /* do nothing */
107     }
108 }
109
110
111 // boot_readsect(dst, src_sect)
112 //   Read disk sector number 'src_sect' into address 'dst'.
113 static void boot_readsect(uintptr_t dst, uint32_t src_sect) {
114     // programmed I/O for "read sector"
115     boot_waitdisk();
116     outb(0x1F2, 1);           // send 'count = 1' as an ATA argument
117     outb(0x1F3, src_sect);    // send 'src_sect', the sector number
118     outb(0x1F4, src_sect >> 8);
119     outb(0x1F5, src_sect >> 16);
120     outb(0x1F6, (src_sect >> 24) | 0xE0);
121     outb(0x1F7, 0x20);       // send the command: 0x20 = read sectors
122
123     // then move the data into memory
124     boot_waitdisk();
125     insl(0x1F0, (void*) dst, SECTORSIZE/4); // read 128 words from the disk
126 }
127
128

```

Mar 29, 21 5:43

**handout10-1.txt**

Page 3/5

```

129 2. Two more examples of I/O instructions
130
131     (a) Reading keyboard input
132
133 The code below is an excerpt from WeensyOS's k-hardware.c
134
135 This reads a character typed at the keyboard (which shows up on the
136 "keyboard data port" (kKEYBOARD_DATAREG)).
137
138 /* Excerpt from WeensyOS x86-64.h */
139 // Keyboard programmed I/O
140 #define KEYBOARD_STATUSREG      0x64
141 #define KEYBOARD_STATUS_READY    0x01
142 #define KEYBOARD_DATAREG        0x60
143
144 int keyboard_readc(void) {
145     static uint8_t modifiers;
146     static uint8_t last_escape;
147
148     if ((inb(KEYBOARD_STATUSREG) & KEYBOARD_STATUS_READY) == 0) {
149         return -1;
150     }
151
152     uint8_t data = inb(KEYBOARD_DATAREG);
153     uint8_t escape = last_escape;
154     last_escape = 0;
155
156     if (data == 0xE0) {           // mode shift
157         last_escape = 0x80;
158         return 0;
159     } else if (data & 0x80) {    // key release: matters only for modifier keys
160         int ch = keymap[(data & 0x7F) | escape];
161         if (ch >= KEY_SHIFT && ch < KEY_CAPSLOCK) {
162             modifiers &= ~(1 << (ch - KEY_SHIFT));
163         }
164         return 0;
165     }
166
167     int ch = (unsigned char) keymap[data | escape];
168
169     if (ch >= 'a' && ch <= 'z') {
170         if (modifiers & MOD_CONTROL) {
171             ch -= 0x60;
172         } else if (!(modifiers & MOD_SHIFT) != !(modifiers & MOD_CAPSLOCK)) {
173             ch -= 0x20;
174         }
175     } else if (ch >= KEY_CAPSLOCK) {
176         modifiers ^= 1 << (ch - KEY_SHIFT);
177         ch = 0;
178     } else if (ch >= KEY_SHIFT) {
179         modifiers |= 1 << (ch - KEY_SHIFT);
180         ch = 0;
181     } else if (ch >= CKEY(0) && ch <= CKEY(21)) {
182         ch = complex_keymap[ch - CKEY(0)].map[modifiers & 3];
183     } else if (ch < 0x80 && (modifiers & MOD_CONTROL)) {
184         ch = 0;
185     }
186
187     return ch;
188 }
189

```

Mar 29, 21 5:43

**handout10-1.txt**

Page 4/5

```

190
191     (b) Setting the cursor position
192
193 The code below is also excerpted from WeensyOS's k-hardware.c. It
194 uses I/O instructions to set a blinking cursor in the upper left of
195 the screen.
196
197 // console_show_cursor(cpos)
198 //   Move the console cursor to position 'cpos', which should be between 0
199 //   and 80 * 25.
200
201 void console_show_cursor(int cpos) {
202     if (cpos < 0 || cpos > CONSOLE_ROWS * CONSOLE_COLUMNS) {
203         cpos = 0;
204
205         outb(0x3D4, 14);           // Command 14 = upper byte of position
206         outb(0x3D5, 0 / 256);     // row 0
207         outb(0x3D4, 15);           // Command 15 = lower byte of position
208         outb(0x3D5, 0 % 256);     // column 0
209     }
210
211
212
213
214

```

Mar 29, 21 5:43

**handout10-1.txt**

Page 5/5

```

215 3. Memory-mapped I/O
216
217     a. Here is a 32-bit PC's physical memory map:
218
219     +-----+ <- 0xFFFFFFFF (4GB)
220     | 32-bit
221     | memory mapped
222     | devices
223     | \/\ / \ / \ / \ / \ / \ / \
224     |
225     | \/\ / \ / \ / \ / \ / \ / \
226     | Unused
227     | +-----+ <- depends on amount of RAM
228
229     | Extended Memory
230
231     | +-----+ <- 0x00100000 (1MB)
232     | BIOS ROM
233     | +-----+ <- 0x000F0000 (960KB)
234     | 16-bit devices,
235     | expansion ROMs
236     | +-----+ <- 0x000C0000 (768KB)
237     | VGA Display
238     | +-----+ <- 0x000A0000 (640KB)
239
240     | Low Memory
241
242     | +-----+ <- 0x00000000
243
244
245
246
247
248 [Credit to Frans Kaashoek, Robert Morris, and Nickolai Zeldovich for
249 this picture]
250
251
252
253     b. Loads and stores to the device memory "go to hardware".
254
255     An example is in the console printing code from WeensyOS. Here is an
256     excerpt from link/shared.ld:
257
258     /* Compare the address below to the map above. */
259     PROVIDE(console = 0xB8000);
260
261     This is an excerpt from lib.c; notice how it uses the address
262     "console":
263
264     /*
265      * prints a character to the console at the specified
266      * cursor position in the specified color.
267      * Question: what is going on in the check
268      * if (c == '\n')
269      * ?
270      * Hint: '\n' is "C" for "newline" (the user pressed enter).
271      */
272     static void console_putchar(printer* p, unsigned char c, int color) {
273         console_printer* cp = (console_printer*) p;
274         if (cp->cursor >= console + CONSOLE_ROWS * CONSOLE_COLUMNS) {
275             cp->cursor = console;
276         }
277         if (c == '\n') {
278             int pos = (cp->cursor - console) % 80;
279             for (; pos != 80; pos++) {
280                 *cp->cursor++ = ' ' | color;
281             }
282         } else {
283             *cp->cursor++ = c | color;
284         }
285     }

```