



- Kernel code: tries matching ^{process.h} ^{int}
 - system calls and returns ^{/.rat}
 - you'll use virtual-memory-map() ^{exception-return} ^{/.rdx}
 - pay attention to the "allocator" argument!
 - make sure your allocator initializes the page table
- sys-page-alloc
~ brk(), mmap()
- NULL vs. non-NULL

process's virtual address space: 3MB. What's the page table structure?



[0, 3MB)
2MB → 3MB


PCB ≡ struct proc
in kernel.h



struct physical_pageinfo {

int8_t owner;
int8_t refcount;


}



one per physical page

bugs


x86-64 - pagetable



512
8 byte-entries

3. I/O arch

NIC



4. CPU/device interaction

A. Mechanics of communication

(a) explicit I/O instructions

outb, inb, outw, inw, ...

examples:

- (i) boot.c
- (ii) keyboard_read.c
- (iii) console_show_cursor

(b) memory-mapped I/O

VPN → PPN

Physical addr → hardware or I/O

~~0xB000~~ 0xB8000
movq %fs, %rax, 0xB000

(c) interrupts

(d) via physical memory

B. Polling vs. interrupts (vs. busy waiting)

It's a tradeoff

interrupts

NIC

millions pkt/sec

10^4 pkts/sec

C. Programmed I/O: CPU writes to devices
reads from devices

DMA: better way if there's a lot of data to move


kernel writes to a device to tell it about DMA

back: DMA → interrupt


DMA actual:

{DMA, programmed I/O} × {polling, interrupts}


(DMA, polling)



5. Device drivers



Machine



Mar 29, 21 5:43

handout10-1.txt

Page 1/5

```

1 CS 202, Spring 2021
2 Handout 10 (Class 16)
3
4 1. Example use of I/O instructions: boot loader
5
6     Below is the WeensyOS boot loader
7
8     It may be helpful to understand the overall picture
9
10    This code demonstrates I/O, specifically with the disk: the
11    bootloader reads in the kernel from the disk.
12
13    See the functions boot_waitdisk() and boot_readsect(). Compare to
14    Figures 36.5 and 36.6 in OSTEP.
15
16 /* boot.c */
17 #include "x86-64.h"
18 #include "elf.h"
19
20 // boot.c
21 //
22 // WeensyOS boot loader. Loads the kernel at address 0x40000 from
23 // the first IDE hard disk.
24 //
25 // A BOOT LOADER is a tiny program that loads an operating system into
26 // memory. It has to be tiny because it can contain no more than 510 bytes
27 // of instructions: it is stored in the disk's first 512-byte sector.
28 //
29 // When the CPU boots it loads the BIOS into memory and executes it. The
30 // BIOS initializes devices and CPU state, reads the first 512-byte sector of
31 // the boot device (hard drive) into memory at address 0x7C00, and jumps to
32 // that address.
33 //
34 // The boot loader is contained in bootstart.S and boot.c. Control starts
35 // in bootstart.S, which initializes the CPU and sets up a stack, then
36 // transfers here. This code reads in the kernel image and calls the
37 // kernel.
38 //
39 // The main kernel is stored as an ELF executable image starting in the
40 // disk's sector 1.
41
42 #define SECTORSIZE      512
43 #define ELFHDR          ((elf_header*) 0x10000) // scratch space
44
45 void boot(void) __attribute__((noreturn));
46 static void boot_readsect(uintptr_t dst, uint32_t src_sect);
47 static void boot_readseg(uintptr_t dst, uint32_t src_sect,
48                          size_t filesz, size_t memsz);
49
50 // boot
51 // Load the kernel and jump to it.
52 void boot(void) {
53     // read 1st page off disk (should include programs as well as header)
54     // and check validity
55     boot_readseg((uintptr_t) ELFHDR, 1, PAGESIZE, PAGESIZE);
56     while (ELFHDR->e_magic != ELF_MAGIC) {
57         /* do nothing */
58     }
59
60     // load each program segment
61     elf_program* ph = (elf_program*) ((uint8_t*) ELFHDR + ELFHDR->e_phoff);
62     elf_program* eph = ph + ELFHDR->e_phnum;
63     for (; ph < eph; ++ph) {
64         boot_readseg(ph->p_va, ph->p_offset / SECTORSIZE + 1,
65                     ph->p_filesz, ph->p_memsz);
66     }
67
68     // jump to the kernel
69     typedef void (*kernel_entry_t)(void) __attribute__((noreturn));
70     kernel_entry_t kernel_entry = (kernel_entry_t) ELFHDR->e_entry;
71     kernel_entry();
72 }
73

```

Monday March 29, 2021

handout10-1.txt

Mar 29, 21 5:43

handout10-1.txt

Page 2/5

```

74
75 // boot_readseg(dst, src_sect, filesz, memsz)
76 // Load an ELF segment at virtual address `dst` from the IDE disk's sector
77 // `src_sect`. Copies `filesz` bytes into memory at `dst` from sectors
78 // `src_sect` and up, then clears memory in the range
79 // `[dst+filesz, dst+memsz)`.
80 static void boot_readseg(uintptr_t ptr, uint32_t src_sect,
81                          size_t filesz, size_t memsz) {
82     uintptr_t end_ptr = ptr + filesz;
83     memsz += ptr;
84
85     // round down to sector boundary
86     ptr &= ~(SECTORSIZE - 1);
87
88     // read sectors
89     for (; ptr < end_ptr; ptr += SECTORSIZE, ++src_sect) {
90         boot_readsect(ptr, src_sect);
91     }
92
93     // clear bss segment
94     for (; end_ptr < memsz; ++end_ptr) {
95         *(uint8_t*) end_ptr = 0;
96     }
97 }
98
99
100 // boot_waitdisk
101 // Wait for the disk to be ready.
102 static void boot_waitdisk(void) {
103     // Wait until the ATA status register says ready (0x40 is on)
104     // & not busy (0x80 is off)
105     while ((inb(0x1F7) & 0xC0) != 0x40) {
106         /* do nothing */
107     }
108 }
109
110
111 // boot_readsect(dst, src_sect)
112 // Read disk sector number `src_sect` into address `dst`.
113 static void boot_readsect(uintptr_t dst, uint32_t src_sect) {
114     // programmed I/O for "read sector"
115     boot_waitdisk();
116     outb(0x1F2, 1); // send `count = 1` as an ATA argument
117     outb(0x1F3, src_sect); // send `src_sect`, the sector number
118     outb(0x1F4, src_sect >> 8);
119     outb(0x1F5, src_sect >> 16);
120     outb(0x1F6, (src_sect >> 24) | 0xE0);
121     outb(0x1F7, 0x20); // send the command: 0x20 = read sectors
122
123     // then move the data into memory
124     boot_waitdisk();
125     insl(0x1F0, (void*) dst, SECTORSIZE/4); // read 128 words from the disk
126 }
127
128

```

Copy to
Figures 36.5 and
36.6 in the book

1/3

Mar 29, 21 5:43

handout10-1.txt

Page 3/5

```

129 2. Two more examples of I/O instructions
130
131 (a) Reading keyboard input
132
133 The code below is an excerpt from WeensyOS's k-hardware.c
134
135 This reads a character typed at the keyboard (which shows up on the
136 "keyboard data port" (KEYBOARD_DATAREG)).
137
138 /* Excerpt from WeensyOS x86-64.h */
139 // Keyboard programmed I/O
140 #define KEYBOARD_STATUSREG 0x64
141 #define KEYBOARD_STATUS_READY 0x01
142 #define KEYBOARD_DATAREG 0x60
143
144 int keyboard_readc(void) {
145     static uint8_t modifiers;
146     static uint8_t last_escape;
147
148     if ((inb(KEYBOARD_STATUSREG) & KEYBOARD_STATUS_READY) == 0) {
149         return -1;
150     }
151
152     uint8_t data = inb(KEYBOARD_DATAREG);
153     uint8_t escape = last_escape;
154     last_escape = 0;
155
156     if (data == 0xE0) { // mode shift
157         last_escape = 0x80;
158         return 0;
159     } else if (data & 0x80) { // key release: matters only for modifier ke
160 ys
161         int ch = keymap[(data & 0x7F) | escape];
162         if (ch >= KEY_SHIFT && ch < KEY_CAPSLOCK) {
163             modifiers &= ~(1 << (ch - KEY_SHIFT));
164         }
165         return 0;
166     }
167
168     int ch = (unsigned char) keymap[data | escape];
169
170     if (ch >= 'a' && ch <= 'z') {
171         if (modifiers & MOD_CONTROL) {
172             ch -= 0x60;
173         } else if (!(modifiers & MOD_SHIFT) != !(modifiers & MOD_CAPSLOCK))
174 {
175             ch -= 0x20;
176         }
177     } else if (ch >= KEY_CAPSLOCK) {
178         modifiers ^= 1 << (ch - KEY_SHIFT);
179         ch = 0;
180     } else if (ch >= KEY_SHIFT) {
181         modifiers |= 1 << (ch - KEY_SHIFT);
182         ch = 0;
183     } else if (ch >= CKEY(0) && ch <= CKEY(21)) {
184         ch = complex_keymap[ch - CKEY(0)].map[modifiers & 3];
185     } else if (ch < 0x80 && (modifiers & MOD_CONTROL)) {
186         ch = 0;
187     }
188
189     return ch;
190 }

```

Mar 29, 21 5:43

handout10-1.txt

Page 4/5

```

190
191 (b) Setting the cursor position
192
193 The code below is also excerpted from WeensyOS's k-hardware.c. It
194 uses I/O instructions to set a blinking cursor in the upper left of
195 the screen.
196
197 // console_show_cursor(cpos)
198 // Move the console cursor to position 'cpos', which should be between 0
199 // and 80 * 25.
200
201 void console_show_cursor(int cpos) {
202     if (cpos < 0 || cpos > CONSOLE_ROWS * CONSOLE_COLUMNS) {
203         cpos = 0;
204     }
205
206     outb(0x3D4, 14); // Command 14 = upper byte of position
207     outb(0x3D5, 0 / 256); // row 0
208     outb(0x3D4, 15); // Command 15 = lower byte of position
209     outb(0x3D5, 0 % 256); // column 0
210 }
211
212
213
214

```

